



## Labor Standards and Safety Division

### Physical Agent Data Sheet (PADS) - Cold Stress

#### Other PADS:

[Cold Stress](#)  
[Hand-Arm Vibration](#)  
[Heat](#)  
[Ionizing Radiation \(PDF\)](#)  
[Lasers](#)  
[Noise](#)  
[Radio Waves](#)  
[Ultraviolet Radiation](#)

[Preventing Hypothermia](#)  
[Treatment of Hypothermia](#)  
[Frostbite](#)  
[Protection from the cold](#)  
[Essential Clothing](#)

[Traveling](#)  
[Special Warnings](#)  
[Other Factors](#)  
[How to Recognize Frostbite](#)  
[Early Treatment](#)

Exposure to cold can cause the body's internal temperature to drop to a dangerously low level. This is called hypothermia. Exposure to temperatures below freezing can cause frostbite of the hands, feet, and face.

### Hypothermia Can Kill

Hypothermia occurs when a person's body loses heat faster than it can be produced. The body's "normal" deep body temperature is 99.6 degrees Fahrenheit. . If your body temperature drops to 95 degrees Fahrenheit, uncontrollable shivering occurs. If cooling continues, these other symptoms may occur:

- Vague, slow, slurred speech
- Forgetfulness, memory lapses
- Inability to use hands
- Frequent stumbling
- Drowsiness
- Exhaustion, collapse
- Unconsciousness
- Death

Hypothermia impairs your judgment. You may not be able to make good decisions about your situation. Preventing hypothermia is the best way to avoid being a victim.

[^back to the top.](#)

### Preventing Hypothermia: Be Prepared

Hypothermia can occur at temperatures above freezing. Cold, wet, windy conditions make prime hypothermia weather.

### *Stay Dry - Avoid Exposure*

Wet clothing draws heat very quickly away from the body. Whenever you may be away from shelter or your vehicle, carry waterproof, windproof outer clothing. Put this clothing on before you get wet. Wear inner clothing which retains warmth even when it's wet, such as wool or polypropylene. Avoid cotton clothing. Down clothing is good for cold, dry weather but it loses almost all insulating value if it gets wet. Wear layers of clothing which may be removed or put back on depending on the degree of physical activity. Being wet from sweat is just as dangerous as being wet from rain or snow.

### *Terminate Exposure*

If you do not have adequate clothing to stay warm and dry, get out of the wind and rain or snow. Return to shelter or make camp while you still have a reserve of energy. Build a fire. Make your camp as secure and as comfortable as possible.

[^back to the top.](#)

## **Treatment of Hypothermia**

Be able to recognize the symptoms of hypothermia in yourself and others. The victim may deny he/she is in trouble. Even mild symptoms demand attention.

1. Get the victim out of wet and windy weather.
2. Remove all wet clothing.
3. If the person is only mildly affected:
  - a. Give warm drinks
  - b. Put into dry clothing and a warm sleeping bag.

If more seriously affected (very clumsy, confused, unable to shiver):

1. Treat very gently.
2. Place the victim naked into a warm sleeping bag.
3. Place a rescuer, also naked, into the same sleeping bag. If you have a double bag, place the victim between two rescuers. Warmth from skin to skin contact is the safest method of rewarming. Any warm objects such as rocks, hot water bottles, or heat packs should be wrapped in towels or clothing. Arrange for evacuation. Do not give warm drinks until the victim has regained a clear level of consciousness, the ability to swallow, and is already starting to warm up.

[^back to the top.](#)

## **Frostbite<sup>1</sup>**

Frostbite is the freezing of some part of the body. Fingers, toes, and even whole arms and legs can be lost as a result of frostbite. Such injuries have happened in cities and villages as well as in more isolated areas of Alaska.

## Protection From the Cold

In extreme cold it is important to prevent heat loss from as many areas of the body as possible. Exposed limbs and head are major areas of heat loss, but keeping enough blood flowing to the hands and feet is the key to preventing frostbite. The trunk and the head, then, should be warm enough so that the brain is able to command the blood vessels in the hands and feet to open up.

## Essential Clothing

This includes thermal underwear, insulated footwear or mukluks with liners, double mittens and a parka, preferably down-filled with a good ruff. A parka which can be opened at the neck to allow heat to escape will prevent overheating and sweating. Quilted or skin pants are necessary if no warm shelter is immediately available. Tight clothes, especially tight gloves or tight boots, should not be worn. They interfere with the blood flow and reduce insulation against the cold.

[^back to the top.](#)

## Traveling

The traveler, even on a snowmobile, or in a heated automobile, should always be prepared to walk in severe cold. This means carrying along proper clothing and more extensive survival gear. If an accident, mechanical breakdown, or other interruption occurs during travel, the clothes you have must provide enough warmth to sustain life. Hands and feet should be well protected at all times to hinder the development of frostbite until help arrives.

## Some Special Warnings

Don't touch cold metal with bare or wet hands. You will freeze to the metal and tear away skin. If necessary, thaw gently with heat, warm water or urine.

Be careful when handling gasoline, kerosene or liquids other than water. Contact at cold temperatures can cause immediate frostbite.

Remember that frostbite is more likely to occur when you are injured, frightened or careless.

[^back to the top.](#)

## Other Factors Leading to Frostbite

Tall thin persons are more likely to get frostbite than those of stocky build.

People in poor physical condition are more susceptible than those in good health.

Certain diseases slow down the blood flow in the hands and feet, especially in elderly people, and encourage frostbite.

---

Heavy smokers often have poor circulation in the vital organs and to the arms and legs, and are also susceptible.

Children and elderly people, unable to produce large amounts of body heat for long periods of time, may experience a lowering of deep body temperature and, ultimately, frostbite.

Alcohol causes the blood vessels to dilate (become larger). This lends a sense of warmth, but it also insures a faster loss of body heat. More important, people act with poor judgment after drinking.

In short, poor circulation and poor production of body heat will lower resistance to frostbite.

[^back to the top.](#)

## How to Recognize Frostbite

Pain in the hands and feet is felt only when the temperature of the tissue is changing very rapidly. There may be no pain with gradual freezing.

Loss of the sensations of touch, pressure, and pain may occur without awareness of any numbness or other sensation. Therefore, it is important to test these sensations often and to wear clothing that is loose and does not restrict the flow of blood to the limbs.

Exposed parts of the body should be inspected routinely. This is done best by a partner. Just before freezing, the skin, especially the face with its many blood vessels, becomes bright red. Then small patches of white appear, as freezing actually occurs.

The skin also becomes less elastic. This is best noted in the finger pads, which remain pitted when touched or squeezed. Any further cooling will surely result in frostbite.

Serious freezing is most common in the feet because of less awareness of them, poor circulation and sensation, and inadequate foot gear. Hands are next in order of serious injury. Exposed head parts are less likely to become frostbitten than feet because they are conditioned to exposure and have a better blood supply.

[^back to the top.](#)

## Early Treatment of Frostbite: Proper Rewarming

1. Next to the extent of freezing, inadequate or improper treatment of a frozen part is the most common cause of serious loss of tissue.
2. In many cases rewarming cannot be done without the part again becoming frozen. For example, removing clothing from other parts of the body to warm a frozen part may only result in the loss of more body heat, greater extent of injury, and the ultimate refreezing of the afflicted part.

Thawing and refreezing should always be avoided. It is best to continue, even if it means walking on a frozen foot, until shelter is available and rewarming can be done satisfactorily.

3. Limbs should be rewarmed in stirred water just above normal body temperature (about 100 - 105 degrees Fahrenheit). Using a thermometer is the only accurate way to measure this temperature. Never try to thaw in cold water or snow. Since feeling is lost, fires, stoves, exhaust pipes, etc., should never be used. Serious damage to the tissue could result.
4. If the major part of the limb is frozen when rewarming is started, deep body temperature will fall as the cooled blood begins to flow throughout the body. To prevent such cooling, warm liquids by mouth should be given. Even total immersion of the body in a warm bath may be necessary.
5. Rewarming is an acutely painful experience and medication to alleviate pain should be given if available. After thawing, a deep aching pain may persist for several days, depending upon severity of the injury. Pain is actually a good sign, since it indicates that nerve function is still present.
6. The afflicted part should be moved gently and voluntarily during rewarming.
7. A dull purple color indicates more serious injury and requires medical attention. So does swelling or blisters. Other means for improving circulation are available but must be administered by medical personnel.

[^back to the top.](#)

## Summary

Most cases of frostbite occur as a result of lack of knowledge, careless preparation, unavoidable accident, or the effects of alcohol on judgment. Intelligent forethought can prevent injury.

If freezing does occur, proper rewarming in warm water will give maximum benefit. The injured limb should be handled gently and a medical judgment be made of the extent of the injury and the need for further treatment.

## Reference

1. Frostbite information compiled and distributed by the Providence Hospital Thermal Unit.

[^back to the top.](#)

[Labor and Workforce Development](#) || [Job Seeker](#) || [Employer](#) || [Worker](#)

---

## **Labor Standards and Safety Division**

### **Physical Agent Data Sheet (PADS)**

#### **- Heat Stress**

<p><b>Other PADS:</b>  <a href="#">Cold Stress</a>  <a href="#">Hand-Arm Vibration</a>  <a href="#">Heat</a>  <a href="#">Ionizing Radiation</a> (PDF)  <a href="#">Lasers</a>  <a href="#">Noise</a>  <a href="#">Radio Waves</a>  <a href="#">Ultraviolet Radiation</a></p>	<p><u><a href="#">Description</a></u>   <u><a href="#">Health Effects—Heat Disorders</a></u>   <u><a href="#">Medical Conditions Aggravated By Exposure to Heat</a></u>   <u><a href="#">Preventing Heat Disorders</a></u></p>	<p><u><a href="#">Acclimatization</a></u>   <u><a href="#">Lessening Stressful Conditions</a></u>   <u><a href="#">Thermal Conditions in the Workplace</a></u>   <u><a href="#">Rest Areas</a></u>   <u><a href="#">Drinking Water</a></u></p>
---	--	--

### **Description**

Heat stress is caused by working in hot environments like laundries, bakeries, or around boilers or incinerators. Four environmental factors affect the amount of heat stress felt by employees in hot work areas: temperature, humidity, radiant heat (such as from the sun or a furnace), and air velocity. How well or how poorly an individual reacts to heat stress is dependent on personal characteristics such as age, weight, fitness, medical condition, and acclimatization.

The body has several methods of maintaining the proper internal body temperature. When internal body temperature increases, the circulatory system reacts by increasing the amount of blood flow to the skin so the extra heat can be given off.

Sweating is another means the body uses to maintain stable internal temperatures. When sweat evaporates, cooling results. However, sweating is effective only if the humidity level is low enough to permit evaporation and if the fluids and salts lost are replaced.

[^back to the top](#)

### **Health Effects—Heat Disorders**

Heat stroke, the most serious health problem for workers in hot environments is caused by the failure of the body's internal mechanism to regulate its core temperature. Sweating stops and the body can no longer rid itself of excess

heat. Signs include: mental confusion, delirium, loss of consciousness, convulsions or coma; a body temperature of 106 degrees Fahrenheit or higher; and hot dry skin which may be red, mottled or bluish. Victims of heat stroke will die unless treated promptly. While medical help should be called, the victim must be removed immediately to a cool area and his/her clothing soaked with cool water. He/she should be fanned vigorously to increase cooling. Prompt first aid can prevent permanent injury to the brain and other vital organs.

Heat exhaustion develops as a result of loss of fluid through sweating when a worker has failed to drink enough fluids or take in enough salt, or both. The worker with heat exhaustion still sweats, but experiences extreme weakness or fatigue, giddiness, nausea, or headache. The skin is clammy and moist, the complexion pale or flushed, and the body temperature normal or slightly higher. Treatment is usually simple: the victim should rest in a cool place and drink salted liquids. Salt tablets are not recommended. Severe cases involving victims who vomit or lose consciousness may require longer treatment under medical supervision.

Heat cramps, painful spasms of the bone muscles, are caused when workers drink large quantities of water but fail to replace their bodies' salt loss. Tired muscles, those used for performing the work, are usually the ones most susceptible to cramps. Cramps may occur during or after working hours and may be relieved by taking salted liquids by mouth or saline solutions intravenously for quicker relief, if medically determined to be required.

Fainting may be a problem for the worker unacclimatized to a hot environment who simply stands still in the heat. Victims usually recover quickly after a brief period of lying down. Moving around, rather than standing still, will usually reduce the possibility of fainting.

Heat rash, also known as prickly heat, may occur in hot and humid environments where sweat is not easily removed from the surface of the skin by evaporation. When extensive or complicated by infection, heat rash can be so uncomfortable that it inhibits sleep and impairs a worker's performance or even results in temporary total disability. It can be prevented by showering, resting in a cool place, and allowing the skin to dry.

[^back to the top](#)

## **Medical Conditions Aggravated By Exposure to Heat**

Persons with heart or circulatory diseases or those who are on "low salt" diets should consult with their physicians prior to working in hot environments.

## **Preventing Heat Disorders**

One of the best ways to reduce heat stress on workers is to minimize heat in the workplace. However, there are some work environments where heat production is difficult to control, such as when furnaces or sources of steam or water are present in the work area, or when the workplace itself is outdoors and exposed to varying warm weather conditions.

---

## **Acclimatization**

Humans are, to a large extent, capable of adjusting to the heat. This adjustment to heat, under normal circumstances, usually takes about 5 to 7 days, during which time the body will undergo a series of changes that will make continued exposure to heat more endurable.

On the first day of work in a hot environment, the body temperature, pulse rate, and general discomfort will be higher. With each succeeding daily exposure, all of these responses will gradually decrease, while the sweat rate will increase. When the body becomes acclimated to the heat, the worker will find it possible to perform work with less strain and distress.

Gradual exposure to heat gives the body time to become accustomed to higher environmental temperatures. Heat disorders in general are more likely to occur among workers who have not been given time to adjust to working in the heat or among workers who have been away from hot environments and who have gotten accustomed to lower temperatures. Hot weather conditions of the summer are likely to affect the worker who is not acclimatized to heat. Likewise, workers who return to work after a leisurely vacation or extended illness may be affected by the heat in the work environment. Whenever such circumstances occur, the worker should be gradually reacclimatized to the hot environment.

[^back to the top](#)

## **Lessening Stressful Conditions**

Many industries have attempted to reduce the hazards of heat stress by introducing engineering controls, training workers in the recognition and prevention of heat stress, and implementing work-rest cycles. Heat stress depends, in part, on the amount of heat the worker's body produces while a job is being performed. The amount of heat produced during hard, steady work is much higher than that produced during intermittent or light work. Therefore, one way of reducing the potential for heat stress is to make the job easier or lessen its duration by providing adequate rest time. Mechanization of work procedures can often make it possible to isolate workers from the heat source (perhaps in an air-conditioned booth) and increase overall productivity by decreasing the time needed for rest. Another approach to reducing the level of heat stress is the use of engineering controls which include ventilation and heat shielding.

## **Number and Duration of Exposures**

Rather than be exposed to heat for extended periods of time during the course of a job, workers should, wherever possible, be permitted to distribute the workload evenly over the day and incorporate work-rest cycles. Work-rest cycles give the body an opportunity to get rid of excess heat, slow down the production of internal body heat, and provide greater blood flow to the skin.

Workers employed outdoors are especially subject to weather changes. A hot spell or a rise in humidity can create overly stressful conditions. The following



practices can help to reduce heat stress:

Postponement of nonessential tasks

Permit only those workers acclimatized to heat to perform the more strenuous tasks, or

Provide additional workers to perform the task keeping in mind that all workers should have the physical capacity to perform the task and that they should be accustomed to the heat.

[^back to the top](#)

## **Thermal Conditions in the Workplace**

A variety of engineering controls can be introduced to minimize exposure to heat. For instance, improving the insulation on a furnace wall can reduce its surface temperature and the temperature of the area around it. In a laundry room, exhaust hoods installed over those sources releasing moisture will lower the humidity in the work area. In general, the simplest and least expensive methods of reducing heat and humidity can be accomplished by:

Opening windows in hot work areas,

Using fans, or

Using other methods of creating airflow such as exhaust ventilation or air blowers.

## **Rest Areas**

Providing cool rest areas in hot work environments considerably reduces the stress of working in those environments. There is no conclusive information available on the ideal temperature for a rest area. However, a rest area with a temperature near 76 degrees Fahrenheit appears to be adequate and may even feel chilly to a hot, sweating worker, until acclimated to the cooler environment. The rest area should be as close to the workplace as possible. Individual work periods should not be lengthened in favor of prolonged rest periods. Shorter but frequent work-rest cycles are the greatest benefit to the worker.

[^back to the top](#)

## **Drinking Water**

In the course of a day's work in the heat, a worker may produce as much as 2 to 3 gallons of sweat. Because so many heat disorders involve excessive dehydration of the body, it is essential that water intake during the workday be about equal to the amount of sweat produced.

Most workers exposed to hot conditions drink less fluids than needed because of an insufficient thirst drive. A worker, therefore, should not depend on thirst to signal when and how much to drink. Instead, the worker should drink 5 to 7

ounces of fluids every 15 or 20 minutes to replenish the necessary fluids in the body. There is no optimum temperature of drinking water, but most people tend not to drink warm or very cold fluids as readily as they will cool ones. whatever the temperature of the water, it must be palatable and readily available to the worker. Individual drinking cups should be provided, never use a common drinking cup.

Heat acclimatized workers lose much less salt in their sweat than do workers who are not adjusted to the heat. The average American diet contains sufficient salt for acclimatized workers even when sweat production is high. If, for some reason, salt replacement is required, the best way to compensate for the loss is to add a little extra salt to the food. Salt tablets should not be used. CAUTION: PERSONS WITH HEART PROBLEMS OR THOSE ON A "LOW SODIUM" DIET WHO WORK IN HOT ENVIRONMENTS SHOULD CONSULT A PHYSICIAN ABOUT WHAT TO DO UNDER THESE CONDITIONS.

[^back to the top](#)

## **Protective Clothing**

Clothing inhibits the transfer of heat between the body and the surrounding environment. Therefore, in hot jobs where the air temperature is lower than skin temperature, wearing clothing reduces the body's ability to lose heat into the air.

When air temperature is higher than skin temperature, clothing helps to prevent the transfer of heat from the air to the body. The advantage of wearing clothing, however, may be nullified if the clothes interfere with the evaporation of sweat.

In dry climates, adequate evaporation of sweat is seldom a problem. In a dry work environment with very high air temperatures, the wearing of clothing could be an advantage to the worker. The proper type of clothing depends on the specific circumstance. Certain work in hot environments may require insulated gloves, insulated suits, reflective clothing, or infrared reflecting face shields. For extremely hot conditions, thermally-conditioned clothing is available. One such garment carries a self-contained air conditioner in a backpack, while another is connected to a compressed air source which feeds cool air into the jacket or coveralls through a vortex tube. Another type of garment is a plastic jacket which has pockets that can be filled with dry ice or containers of ice.

[^back to the top](#)

## **Recommended Exposure Limits**

These Threshold Limit Values (TLVS) refer to heat stress conditions under which it is believed that nearly all workers may be repeatedly exposed without adverse health effects. The TLVs shown in Table I are based on the assumption that nearly all acclimatized, fully clothed workers with adequate water and salt intake should be able to function effectively under the given working conditions without exceeding a deep body temperature of 38 degrees Celsius (100.4 degrees Fahrenheit).

Since measurement of deep body temperature is impractical for monitoring the workers' heat load, the measurement of environmental factors is required which most nearly correlate with deep body temperature and other physiological responses to heat. At the present time, Wet Bulb Globe Temperature Index (WBGT) is the simplest and most suitable technique to measure the environmental factors. WBGT values are calculated by the following equations:

Outdoors with solar load:  $WBGT = 0.7 NWB + 0.2 GT + 0.1 DB$

Indoors or Outdoors with no solar load:  $WBGT = 0.7 NWB + 0.3 GT$

Where: WBGT = Wet Bulb Globe Temperature Index

NWB = Natural Wet Bulb Temperature

DB = Dry Bulb Temperature

GT = Globe Temperature

The determination of WBGT requires the use of a black globe thermometer, a natural (static) wet-bulb thermometer, and a dry bulb thermometer.

Higher heat exposures that shown in Table I are permissible if the workers have been undergoing medical surveillance and it has been established that they are more tolerant at work in heat than the average worker. Workers should not be permitted to continue their work when their deep body temperature exceeds 38.0 degrees Celsius (100.4 degrees Fahrenheit).

[^back to the top](#)

<b>Table 1</b> <b>Permissible Heat Exposure Threshold Limit Values</b> <b>(Values are given in degrees Centigrade WBGT (Fahrenheit))</b>			
	Work Load		
Work- Rest Regimen	Light	Moderate	Heavy
Continuous work	30.0 (86.0)	26.7 (80.1)	25.0 (77.0)
75% Work, 25% Rest/Hour	30.6 (87.1)	28.0 (82.4)	25.9 (78.6)
50% Work, 50% Rest/Hour	31.4 (88.5)	29.4 (85.0)	27.9 (82.2)
25% Work, 75% Rest/Hour	32.2 (90.0)	31.1 (88.0)	30.0 (86.0)

## References

1. "Working in Hot Environments," US Department of Health and Human Services, Public Health Service, Centers for Disease Control, National Institute for Occupational Safety and Health, 1986.

2. "Threshold Limit Values and Biological Exposure Indices for 1986 - 1987," American Conference of Governmental Industrial Hygienists, 6500 Glenway Avenue, Building D-7, Cincinnati, OH 45211-4438.

[^back to the top](#)

---

[Labor and Workforce Development](#) || [Job Seeker](#) || [Employer](#) || [Worker](#)

## **Labor Standards and Safety Division**

### **Physical Agent Data Sheet (PADS) - Noise**

**Other PADS:**

[Cold Stress](#)  
[Hand-Arm Vibration](#)  
[Heat](#)  
[Ionizing Radiation](#) (PDF)  
[Lasers](#)  
 Noise  
[Radio Waves](#)  
[Ultraviolet Radiation](#)

[Description](#)  
[Health Effects](#)  
[Hearing](#)  
[Other Effects](#)  
[Permissible](#)  
[Exposure Limit](#)  
[Protective](#)  
[Measures](#)

### **Description**

Sound is created when a vibrating source (like a bell, motor or a stereo speaker) sends sound waves through the air to your ear. Every sound has two aspects: its pitch (frequency) and its loudness (intensity). On a stereo, frequency is determined by the bass/treble control. Intensity is determined by the volume control. Noise (unwanted sound) is usually made up of many frequencies. The disturbing and harmful effects of noise depend both on the loudness and the frequency of the tones making up noise.

Loudness is measured in units called decibels (dB). A conversational voice is about 65 dB. A shout is 90 dB or greater.

Frequency is measured in units called Hertz (Hz). The frequency of a locomotive horn is about 250 Hz. The frequency of a table saw is about 4,000 Hz.

[^back to the top.](#)

### **Health Effects**

Excessive noise can destroy the ability to hear, and may also put stress of other parts of the body, including the heart.

For most effects of noise, there is no cure, so that prevention of excessive noise exposure is the only way to avoid health damage.

*Hearing*

The damage done by noise depends mainly on how loud it is and on the length of exposure. The frequency or pitch can also have some effect, since high-pitched sounds are more damaging than low-pitched sounds.

Noise may tire out the inner ear, causing temporary hearing loss. After a period of time away from the noise hearing may be restored. Some workers who suffer temporary hearing loss may find that by the time their hearing returns to normal, it is time for another work shift so, in that sense, the problem is "permanent."

With continual noise exposure, the ear will lose its ability to recover from temporary hearing loss, and the damage will become permanent. Permanent hearing loss results from the destruction of cells in the inner ear, cells which can never be replaced or repaired. Such damage can be caused by long-term exposure to loud noise or, in some cases" by brief exposures to very loud noises.

Normally, workplace noise first affects the ability to hear high frequency (high-pitched) sounds. This means that even though a person can still hear some noise, speech or other sounds may be unclear or distorted.

Workers suffering from noise-induced hearing loss may also experience continual ringing in their ears, called "tinnitus." At this time, there is no cure for tinnitus, although some doctors are experimenting with treatment.

[^back to the top.](#)

### *Other Effects*

Although research on the effects of noise is not complete, it appears that noise can cause quickened pulse rate, increased blood pressure and a narrowing of the blood vessels over a long period of time, these may place an added burden on the heart.

Noise may also put stress on other parts of the body by causing the abnormal secretion of hormones and tensing of the muscles.

Workers exposed to noise sometimes complain of nervousness, sleeplessness and fatigue. Excessive noise exposure also can reduce job performance and may cause high rates of absenteeism.

[^back to the top.](#)

## **Permissible Exposure Limit**

The Action level for noise is an average noise level of 85 dB for an eight-hour day. When employees are exposed to noise levels, which exceed the Permissible Exposure Limit, the employer must install or use engineering or administrative controls to lower the noise levels. While these controls are being designed or

installed employees must wear hearing protection. If the controls still do not reduce noise exposures to below 90 dB, hearing protection must continue to be worn.

[^back to the top.](#)

## **Protective Measures**

Suitable hearing protectors (earplugs or muffs) must be made available at no cost to employees who are exposed to an average of 85 dB or greater for an eight-hour day. Employees must be given the opportunity to select from three different types of appropriate hearing protectors.

Hearing tests (audiometric exams) must be given to employees who are exposed to an average of 85 dB or greater for an eight-hour day. Hearing tests will show whether employees are experiencing any hearing losses. Hearing tests are also useful in showing how well the earplugs and earmuffs are working. Hearing tests must be given annually.

Employees should also receive training in the effects of noise on hearing, an explanation of the hearing tests, and instruction on the proper fitting and care of earplugs or muffs.

Noise away from work can also cause hearing loss. Hearing protectors should be worn when operating noisy equipment or tools such as chain saws, brush cutters, power lawn mowers, or when using firearms.

Refer to Alaska Administrative Code, Occupational Health and Environmental Control 04.0104 for specific regulations on Noise Exposure and Hearing Conservation Programs.

[^back to the top.](#)

[Labor and Workforce Development](#) || [Job Seeker](#) || [Employer](#) || [Worker](#)

---

---

## **Labor Standards and Safety Division**

### **Physical Agent Data Sheet (PADS)**

#### **- Hand-Arm Vibration**

Description  
Health Hazards  
Vibration Syndrome  
Vibration Induced  
White Finger  
Stages

Carpal Tunnel Syndrome  
Preventing Hand-Arm Vibration  
Diseases  
Recommended Exposure  
Limits

### **Description**

Hand-arm vibration is caused by the use of vibrating hand-held tools, such as pneumatic jack hammers, drills, gas powered chain saws, and electrical tools such as grinders. The nature of these tools involves vibration (a rapid back and forth type of motion) which is transmitted from the tool to the hands and arms of the person holding the tool.

### **Health Hazards**

Vibration Syndrome and Vibration-Induced White Finger (VWF) are the major health hazards related to the use of vibrating tools. Carpal Tunnel Syndrome is another health problem that has been linked in one study to the use of smaller hand-held vibrating tools.

[^back to the top](#)

#### *Vibration Syndrome*

Vibration Syndrome is a group of symptoms related to the use of vibrating tools and includes -some or all of the following: muscle weakness, muscle fatigue, pain in the arms and shoulders, and vibration-induced white finger. Many researchers believe that other symptoms--headaches, irritability, depression, forgetfulness, and sleeping problems--should also be included in descriptions of Vibration Syndrome.

#### *Vibration-Induced White Finger*

Vibration-Induced White Finger (VWF), also known as "Dead Finger" or "Dead Hand" is the result of impaired circulation (poor blood supply in the fingers, caused



by the prolonged use of vibrating tools. VWF may appear after only several months on the job, or may not appear until twenty to forty years on the job.

The harmful health effects of vibrating tools are related to the length of time that a worker has been using vibrating tools and to the frequency of the vibration (how fast the tool goes back and forth). The longer a person uses a vibrating tool, and the faster the tool vibrates, the greater the risk of health effects. The length of the initial symptom-free period of vibration exposure (i.e., from first exposure to the first appearance of a white finger) is known as the latent interval. It is related to the intensity of the vibration - the shorter the latent period, the more severe the resulting VWF if vibration exposure continues.

Temporary tingling or numbness during or soon after use of a vibrating hand tool is not considered to be VWF, however tingling and numbness in the fingers lasting more than an hour after finishing work may indicate early stages of VWF. Table 1 lists the stages that Vibration White Finger may progress through if exposure continues.

[^back to the top](#)

<p style="text-align: center;"><b>Table 1</b>  <b>Stages of Vibration White Finger</b>  <b>(Taylor-Pelmeur System)</b></p>		
<b>Stage</b>	<b>Condition of Fingers</b>	<b>Work &amp; Social Interference</b>
00	No tingling, numbness or blanching of fingers	No complaints
OT	Intermittent tingling	No interference with activities
ON	Intermittent numbness	No interference with activities
TN	Intermittent tingling and numbness	No interference with activities
1	Blanching of a fingertip with or without tingling and/or numbness	No interference with activities
2	Blanching of one or more fingers beyond tips, usually during winter	Possible interference with activities outside work, no interference at work
3	Extensive blanching of fingers; frequent episodes in both summer and winter	Definite interference at work, at home, and with social activities; restriction of hobbies
4	Extensive blanching of most fingers; frequent episodes in both summer and winter	Occupation usually changed because of severity of signs and symptoms

The technical name for VWF is Raynaud's Syndrome of Occupational Origin. Raynaud's Syndrome may also occur in people who do not use vibrating hand-held tools. Several different kinds of medical illnesses can cause Raynaud's Syndrome. Raynaud's Syndrome also appears in some people who are otherwise entirely healthy.

It is important that people with Raynaud's Syndrome avoid the extensive use of vibrating tools because they can develop the most severe complications of VWF

very quickly.

Many of the symptoms of Vibration Syndrome will disappear shortly after a worker stops using the types of tools which transmit vibration to the hands and arms. Fatigue and muscular pain in the arms and shoulders will generally disappear. In the early stages, if a worker stops using vibrating tools, VWF will not get any worse and may get slightly better.

### *Carpal Tunnel Syndrome*

Carpal Tunnel Syndrome (CTS) is a group of symptoms in the hand which arise from pressure on one of the nerves which passes through the palm side of the wrist. The early symptoms are similar to the early symptoms of white finger and consist of tingling in the fingers. For the most part only the thumb, index, and middle fingers are affected in CTS. Later, symptoms can progress to numbness. Pain in the wrist and fingers may also develop. CTS may occur in people using small hand tools like pneumatic screwdrivers. Carpal Tunnel Syndrome also occurs among people having repetitive motion of the wrist or fingers, such as using a cash register, or picking fish from a net; or with forceful motion of the wrist, such as in using a wrench. Pinching or flexing with the wrist bent upwards, downwards, or sideways increases the occurrence of CTS.

The symptoms of CTS are frequently worse at night and a person may be awakened from sleep by pain or the feeling of pins and needles in fingers, hand or wrist.

Carpal Tunnel Syndrome may improve if diagnosed in the early stages and exposure to the type of activity which caused it is stopped. In moderate cases most of the symptoms of CTS can be relieved by a surgical operation which relieves the pressure on the nerve which causes the CTS symptoms. If the surgery is performed too late, only some of the symptoms may be relieved. In very severe cases the symptoms are irreversible and may include weakness of the hand due to loss of muscle function.

[^back to the top](#)

## **Preventing Hand-Arm Vibration Diseases**

### *Job Modification to Reduce Vibration Exposure*

Wherever possible, jobs should be redesigned to minimize the use of hand-held vibrating tools. Where job redesign is not feasible, ways to reduce tool vibration should be found. Where practical, substitute a manual tool for a vibrating tool. Whenever possible, high vibration tools should be replaced by improved, low vibration tools designed to absorb vibration before it reaches the handgrip.

Determine vibration exposure times and introduce work breaks to avoid constant, continued vibration exposure. A worker who is using a vibrating tool continuously should take a 10 minute break after each hour of using the tool.

### *Medical Evaluation*

Workers whose occupations place them at risk for developing VWF should have pre-employment physicals and thereafter should be checked at least annually by

---

doctors who know about the diagnosis and treatment of VWF. Diagnostic tests which can be used include plethysmography, arteriography, skin thermography, and sensory tests,, such as two point discrimination depth sense, pinprick touch and temperature sensation. X-rays may also be useful.

Workers that have a past history of abnormalities in blood circulation and especially workers who have Raynaudis Syndrome should not be permitted to use vibrating hand-held tools. Workers who have moderate to severe symptoms of VWF should be reassigned to work which removes them from further direct exposure to vibrating tools.

If workers develop symptoms of tingling or numbness, or if their fingers occasionally become white or blue, or painful especially when cold, they should be examined by a doctor who knows about the diagnosis and treatment of VWF and CTS.

### *Work Practices*

Workers using vibrating hand-held tools should wear multiple layers of warm gloves and should wear anti-vibration gloves whenever possible. Before starting the job, warm the hands. This is especially important when it is cold. workers using vibrating tools should not allow the hands to become chilled. If the hands of a worker using vibrating tools become wet or chilled, he should dry them and put on dry, warm gloves before resuming exposure to vibration. Workers exposed to cold should dress adequately to keep the whole body warm because low body temperature can make a worker more susceptible to VWF.

A worker using a vibrating hand-held tool should let the tool do the work by grasping it as lightly as possible, consistent with safe work practice. The tighter the tool is held, the more vibration is transmitted to the fingers and hand. The tool should rest on a support or on the workpiece as much as possible. The tool should be operated only when necessary and at the minimum speed (and impact force) to reduce vibration exposure.

Tools should be regularly maintained to keep vibration to a minimum. Keeping chisels and chainsaws sharp, for example, will reduce vibration. Using new grinder wheels will also reduce vibration.

### *Education*

Employees who use or will be using vibrating hand-held tools should receive training about the hazards of vibration and they should be taught how to minimize the ill effects of vibration.

Smokers are much more susceptible to VWF that non-smokers, and the VWF in smokers is usually more severe, therefore workers who use vibrating hand-held tools should not smoke.

[^back to the top](#)

## **Recommended Exposure Limits**

Table 2 contains the American Conference of Governmental Industrial Hygienists (ACGIH) recommendations on the limits for exposure of the hand to vibration.

---


**Table 2**  
**Threshold Limit Values for Exposure of the Hand**  
**to Vibration in Either  $X_h$ ,  $Y_h$ ,  $Z_h$ , Directions**

Total Daily Exposure Duration <sup>a</sup>	Values of the Dominant, <sup>b</sup> Frequency-Weighted, rms, Component Acceleration Which Shall Not be Exceeded $a_k$ , ( $a_{keg}$ )	
	$m/s^2$	$g^c$
4 hours and less than 8	4	0.40
2 hours and less than 4	6	0.61
1 hour and less than 2	8	0.81
less than 1 hour	12	1.22

a The total time vibration enters the hand per day, whether continuously or intermittently.

b Usually one axis of vibration is dominant over the remaining two axes. If one or more vibration axes exceeds the Total Daily Exposure then the TLV has been exceeded.

c  $g = 9.81 \text{ m/s}^2$  . d



Biodynamic and basicentric coordinate systems for the hand, showing the directions of the acceleration components (ISO 5349 and ANSI S3.34-1986).

[^back to the top](#)